

# UNIT 7

## INTRODUCTION TO ORGANIC CHEMISTRY

### PART 2 – CRUDE OIL: SOURCES AND USES OF ALKANES



#### Contents

1. Crude Oil
2. Combustion of Alkanes

Key words: petroleum, fractional distillation, cracking, reforming, combustion, fuel, petrochemical, octane number

# 1) Crude Oil

## a) Introduction

The vast majority of carbon-containing compounds in widespread use have been made from **crude oil**. Crude oil is also known as **petroleum**.

Crude oil is a mixture of alkanes, most of which are unbranched and contain 20+ carbon atoms.


Each of the hydrocarbons present in crude oil has a slightly different use. Mixed together they are of no use at all. It is necessary, therefore, to separate them before they can be used productively. Crude oil is separated into its different components by a process called **fractional distillation**.

The products of fractional distillation are often converted into other, even more useful hydrocarbons by a process called **cracking**.

## b) Fractional distillation

The different hydrocarbons in crude oil have different boiling points. This is because the chain length varies. The greater the number of carbon atoms in the chain, the longer the chain length. This results in more Van der Waal's forces acting between the molecules and a greater intermolecular attraction. Thus more energy is needed to separate the molecules and the boiling point is higher. It is the difference in boiling points of the different hydrocarbons in crude oil which is used to separate them from each other.

The crude oil is passed into a tall tower called a **fractionating column**. This is very hot near the base but much cooler near the top. When the crude oil is passed into the tower, near the bottom, most of the mixture boils and starts to rise up the tower. As they rise up the tower, they start to cool down and will gradually condense back into liquid form. They are then tapped off. The larger hydrocarbons, with higher boiling points, will condense first and be tapped off near the base of the column. The smaller hydrocarbons, with smaller boiling points, will condense later and be tapped off near the top of the column. Thus the separation is achieved. Not that the process involves breaking **intermolecular forces** only; the molecules themselves are unaffected by this process.



This process does not actually separate the crude oil mixture into pure hydrocarbon components, but into mixtures called **fractions**. **Fractions are mixtures of hydrocarbons with similar boiling points**. In many cases these fractions can be used directly, but sometimes further separation is required into purer components.

The most important fractions and their main uses are summarised as follows:

#### Fractions from crude oil

Name of fraction	Boiling range / °C	Number of hydrocarbons	Uses
Liquefied petroleum gas	Less than 25	1 – 4	Gas for camping/ cooking
Petrol or gasoline			Fuel for cars etc
Naphtha			Petrochemicals
Kerosine or paraffin			Plane fuel, petrochemicals
Diesel or gas oil			lorry, central heating fuel
Mineral/lubricating oil			Lubrication, petrochemicals
Fuel oil			Ship fuel, power stations
Wax and grease			Candles, grease, polish
Bitumen or tar			Road surfaces, roofing
	Above 450	More than 50	

The term **petrochemical** means that the compounds are converted into other chemicals for use as solvents, paints and various other things.

#### c) Cracking

Although all of the fractions produced from crude oil have their uses, some of the fractions are produced in greater quantities than needed, whilst others are not produced in sufficient quantities. The table below gives an example of the difference between the supply and demand of some important fractions:

#### Supply and demand for fractions

Fraction	Approximate supply/%	Approximate demand/%
Liquefied petroleum gases	2	4
Petrol and naphtha	16	27
Kerosine	13	8
Gas oil	19	23
Fuel oil and bitumen	50	38

This disparity can be corrected by breaking up some larger hydrocarbons in fuel oil into the smaller ones found in gas oil, or by breaking up some hydrocarbons in kerosene into the smaller ones found in petrol, naphtha or the liquefied petroleum gases. In other words the larger fractions (for which supply exceeds demand) can be broken up into smaller fractions (for which demand exceeds supply).

The process by which this is carried out is called **cracking**.



Cracking has the added advantage of producing other useful hydrocarbons not naturally present in crude oil, such as **alkenes** (widely used as petrochemicals), **cycloalkanes** and **branched alkanes** (widely used in motor fuels).

Thus cracking is important for two reasons:

- It converts low-demand fractions into higher demand fractions
- It makes useful hydrocarbons not naturally found in crude oil

Cracking involves the breaking of C-C bonds to form smaller molecules. C-C bonds are weaker than C-H bonds and so break more easily when heated.

The conditions required for cracking are a **high temperature** and a **catalyst**.



Cracking always produces one shorter alkane molecule and at least one alkene.


Two products: one alkane and one alkene

Three products: one alkane and two alkenes

Four products: one alkane and three alkenes etc

#### d) Reforming

Cracking produces shorter, more useful alkanes. But most of the products of cracking are aliphatic unbranched alkanes. Alicyclic alkanes tend to make better fuels, and so it is commercially useful to convert unbranched alkanes into alicyclic alkanes:



Eg

Reforming also produces **hydrogen** gas, which can be used to make ammonia and various other important petrochemicals.

**Test Your Progress: Topic 7 Part 2 Exercise 1**

1. Petroleum is separated into its fractions by fractional distillation
  - a) What are fractions?
  - b) Explain how a fractionating column works in five key points.
  - c) Write a list of five fractions, in order of increasing boiling point, and give a use for each.
  - d) Why is fractional distillation important?
  
2. Many of the fractions are then subjected to processes called cracking and reforming.
  - a) Write two different equations to show the cracking of decane ( $C_{10}H_{22}$ ).
  - b) Write an equation to show the cracking of docecane ( $C_{12}H_{26}$ ) into three different products.
  - c) Write an equation to show the reforming of hexane ( $C_6H_{14}$ ).
  - d) Explain why cracking and reforming are important.

## 2) Combustion of Alkanes

### a) Alkanes as fuels

Many of the fractions produced from crude oil are used as fuels. These fractions include:

fraction	Uses
Liquefied petroleum gases	Camping gas, cooking gas
Petrol	Fuel for cars, motorbikes and machines
Kerosine	Fuel for aeroplanes, lamps, ovens
Diesel	Fuel for lorries, and central heating systems
Fuel oil	Fuel for ships, power stations
Wax	Fuel for candles

A fuel is a something that can be changed in a reacting vessel to produce useful energy.

Hydrocarbons, and especially alkanes, will react with oxygen in the air to give carbon dioxide and water. A reaction with oxygen is known as **combustion**. As alkanes are unreactive the reaction needs heat or a spark to get going.

These reactions are very **exothermic**, which means that heat energy is released. This heat energy can be used for direct heating (eg camping gas, central heating, candles). It can also be converted into mechanical energy (eg cars, lorries, ships), or even electrical energy (eg power stations).

Typical examples of combustion reactions include:

Reaction	Enthalpy change/ $\text{kJmol}^{-1}$
$\text{CH}_4 + 2\text{O}_2 \rightarrow \text{CO}_2 + 2\text{H}_2\text{O}$	-890
$\text{C}_4\text{H}_{10} + 6\frac{1}{2}\text{O}_2 \rightarrow 4\text{CO}_2 + 5\text{H}_2\text{O}$	-2877
$\text{C}_8\text{H}_{18} + 12\frac{1}{2}\text{O}_2 \rightarrow 8\text{CO}_2 + 9\text{H}_2\text{O}$	-5470

The release of heat energy during these combustion reactions results in their widespread use as fuels.

**b) Pollution problems associated with burning hydrocarbons****(i) carbon dioxide**

Although carbon dioxide is not poisonous and is naturally removed from the atmosphere by plants, the enormous quantities of hydrocarbons burned in recent years has caused carbon dioxide levels to rise significantly.

Carbon dioxide, along with various other compounds, prevents the earth's heat from escaping into space and is resulting in an increase in the earth's temperature. This is known as **global warming**. The result is the melting of the polar ice caps which is likely to cause severe flooding in the future, as well as serious damage to numerous ecosystems.

Gases which contribute towards global warming are known as **greenhouse gases**.

**(ii) Water vapour**

Water vapour is also produced in large quantities as a result of combustion of hydrocarbons and is also a **greenhouse gas**.

**(iii) carbon monoxide and carbon**

The combustion of hydrocarbons to produce carbon dioxide and water is called **complete combustion**, and it requires a lot of oxygen. If oxygen is not present in sufficiently large quantities, carbon monoxide or carbon is produced instead of carbon dioxide. This is called **incomplete combustion**.

Examples of incomplete combustion reactions are:

$C_4H_{10} + 4\frac{1}{2}O_2 \rightarrow 4CO + 5H_2O$	Incomplete combustion
$C_4H_{10} + 2\frac{1}{2}O_2 \rightarrow 4C + 5H_2O$	Incomplete combustion
$C_8H_{18} + 10\frac{1}{2}O_2 \rightarrow 8CO + 9H_2O$	Incomplete combustion
$C_8H_{18} + 8\frac{1}{2}O_2 \rightarrow 8C + 9H_2O$	Incomplete combustion

The less oxygen that is available, the more likely it is that incomplete combustion will occur. This is a particular problem in internal combustion engines where the air supply is limited. Incomplete combustion is a problem for three reasons:


- Less energy is released by incomplete combustion than by complete combustion.
- Carbon monoxide is a pollutant – it is absorbed by the blood in place of oxygen, and hence reduces the ability of the blood to carry oxygen causing suffocation and eventually death.
- Carbon particles can cause breathing difficulties and cancer.

It is therefore desirable to ensure that the air supply is as good as possible when burning hydrocarbon fuels.

Occasionally incomplete combustion is desirable – such as with a Bunsen burner. Closing the air hole produces a yellow flame (the yellow colour results from hot carbon particles) and this makes the flame more visible and causes a more gentle heat. Usually, however, complete combustion is considered more desirable.

(iv) sulphur dioxide



Most crude oil deposits contain sulphur as an impurity. Oil refineries are increasingly treating the petrol fractions to lower the sulphur content, but some sulphur is still present in most hydrocarbon fuels. When the fuel is burned, the sulphur also burns, producing sulphur dioxide:



This gas dissolves in rainwater forming a very acidic solution, known as **acid rain**. This causes various problems, including erosion of buildings and statues, killing of plants and trees, and killing of fish through contamination of lakes.

(v) oxides of nitrogen

Most fuels are not burned in pure oxygen but in air, which contains 80% nitrogen. Although nitrogen is not a reactive gas, the high temperatures and the spark in combustion engines cause some of the nitrogen to react with the oxygen to produce nitric oxide and nitrogen dioxide:



Nitrogen dioxide ( $\text{NO}_2$ ) also dissolves in rainwater to form an acidic solution and contributes to the problem of **acid rain**.

(vi) unburned hydrocarbons

Some of the hydrocarbon fuel is vaporised in the engine but escapes before it is burned. These unburned hydrocarbons cause various problems. They are toxic and can cause cancer if breathed in.




### c) Quality of Petrol

In most internal combustion engines, petrol is first compressed and then ignited. It is important that the fuel does not self-ignite before it has been fully compressed, as this has an adverse effect on the performance of the engine. The self-ignition of a fuel before it has been fully compressed is known as **knocking**.

Petrochemical companies are constantly trying to reduce knocking by changing the composition of the petrol. The ability of a fuel to resist knocking is known as its **octane number**.

Most traditional petrols are a mixture of heptane and 2,2,4-trimethylpentane (also known as iso-octane).



2,2,4-trimethylpentane is resistant to knocking and is given an octane number of 100.

Heptane is susceptible to knocking and is given an octane number of 0.

All other fuels are allocated an octane number based on their resistance to knocking compared to 2,2,4-trimethylpentane and heptane.

A fuel with an octane number of 95 is slightly less resistant to knocking than 2,2,4-trimethylpentane but much more resistant to knocking than heptane.

#### Test Your Progress: Topic 7 Part 2 Exercise 2

- Write equations to show:
  - the complete combustion of heptane
  - the incomplete combustion of butane (to make CO)
  - the incomplete combustion of hexane (to make C)
- Identify five pollutants made during the combustion of alkanes and state how each pollutant is formed.
- Explain the meaning of the term “octane number”.